

Release Notes for Codesys 3.5.3.52

Datum: 08.11.2016

Changes for Codesys 3.5.3.52

- Update: Include BSP 1.4.1 for OPUS A6
- Fix: Remove the 10ms fix update interval for the target visualization
- Feature: New hardware variants supported
- Fix: Only placeholder includes in the library manager
- Feature: Add new functions to read and write the state of the version control (red screen at boot)
- Change: System environments are used instead of set variables in the start script
- Fix: Object and scroll limits in portrait PDF reader fixed
- Change: Kernel module updated to match BSP 1.4.0

Changes for Codesys 3.5.3.51

- fix systeminfo
- fix systeminfo in device description
- change ignore invalid channels for camera
- fix video object - set settings
- fix ethernet set ip/mode table/function
- fix systeminfoevent function, default values and limit checks
- fix screenshot function, wrong buffer length
- fix device settings table CAN baudrate settings
- update service project, automatic release test
- change limit write access to CODESYSControl.cfg
- change add update cycle to device settings table (systeminfo)
- change add system info events
- fix internal memory leak
- change remove WE out of event names
- fix j1939 license
- change new name for Video, PDF and WEBBrowser object
- change pipe codesys output to /dev/null
- fix remove error output from checkusb function in case that there is no USB stick

Changes for Codesys 3.5.3.30

- fix RGBLED, clear if not supported
- fix filter settings for a3 eco devices
- fix CoDeSys Hotkeys
- fix video crash
- fix daemon stop/start during backup

Changes for Codesys 3.5.3.0

- fix pdf crash
- fix reconnect to power management on object create
- fix 100% CPU load on daemon restart
- fix service keys

Changes for Codesys 3.5.2.0 - 3

- fix PDFReader memory
- fix IOKeys startup
- fix start scripts
- fix infotousb

Changes for Codesys 3.5.2.0 - 2

- change remove serial settings out of the table
- change set default zoom for pdf object to 10
- Fix: create backup changes startscreen
- Fix update daemon start
- Fix segfaults in PDFObject
- Fix pdf reader size of frame
- Fix pfd no text shown
- Fix pdf wrong parameter for invalid files
- Fix pdf wrong value for page parameter
- Fix pdf blocks new download
- Fix pdf zoom not updated with bestfit methods
- Fix pdf invalid zoom not ignored